2/21/2016 Black Box: PID

PID

Macros

#define **DEFAULT_TEMP** (75)

Default desired temperature of black box.

Functions

```
voidtaskPID ()uint32_tgetTemperatureTarget ()voidsetTemperatureTarget (uint32_t temperature)floatgetPComponent ()floatgetIComponent ()floatgetDComponent ()floatgetPIDChange ()
```

Detailed Description

PID.c - PID controller module.

PIDman.c - PID controller management module.

Function Documentation

float getDComponent ()

float getDComponent()

This method is used to retrieve the contribution of the D component to the total change requested by the PID controller.

Returns

The current D contribution to the change requested by the PID controller.

2/21/2016 Black Box: PID

float getlComponent ()

float getIComponent()

This method is used to retrieve the contribution of the I component to the total change requested by the PID controller.

Returns

The current I contribution to the change requested by the PID controller.

float getPComponent ()

float getPComponent()

This method is used to retrieve the contribution of the P component to the total change requested by the PID controller.

Returns

The current P contribution to the change requested by the PID controller.

float getPIDChange ()

float getPIDChange()

This method is used to retrieve the total change requested by the PID controller.

Returns

The current change requested by the PID controller.

uint32_t getTemperatureTarget()

uint32 t getTemperatureTarget()

This method is used to retrieve the current target temperature of the PID controller.

Returns

The current temperature target.

2/21/2016 Black Box: PID

void setTemperatureTarget (uint32_t temperature)

void setTemperatureTarget()

This method is used to set the target temperature of the PID controller.

Parameters

temperature is the new target temperature.

Returns

None.

void taskPID ()

void taskPID()

This task compares the temperature value in *temp_queue*, or the measured temperature inside the black box, and compares it to the desired black box temperature. Using the difference between measured and desired temp, a new ratio of heater on/off time is created. This ratio is stored in PWM_ratio for use by the power driver module to control the heater and adjust black box temp as needed. The desired temp will default to **DEFAULT_TEMP** unless the user has specified a desired temp.

Returns

None.

Generated by @@XXXQQQ 1.8.11